# Chapter 7 - Setting Up Freight Cars

One of the things we are still missing in order to make things happen on our railroad is freight cars. We'll go ahead and set up our freight cars now. Once you see how relatively easy it is to do, the inclination will be there to enter all of your cars, but I urge you to restrain yourself and only enter a few to start with as it will make troubleshooting much easier.

For now, let's ignore the industries that currently exist in Actonvale, and look at the two that we've set up in Berwick. Wilson & Sons Scrap Metal (for short, we'll just call it Wilsons) ships loads of scrap iron, etc. and industries of this nature usually ship their loads in open gondolas. Wilsons does not normally get any loads in.

North Star Engineered Lumber (NSEL for short) needs to receive two different materials for the joists – the dimensional lumber and the OSB. From time to time they also need to get the adhesive that is used to hold the joist pieces together. The dimensional lumber is usually shipped on center beam flat cars. I'm sure you've seen these with the loads of lumber wrapped in colorful waterproof wrappers advertising the lumber producer (Canfor, Weyerhaeuser, etc). The OSB is usually shipped in box cars, normally with double doors. Occasionally the OSB will be shipped in 'all door' type cars – ones where the entire side of the box car can be opened. Depending on the size of the operation, the adhesive may be shipped in tank cars or in drums in box cars. NSEL is small enough that we'll supply it via box cars. Once the joists have been manufactured, NSEL needs to ship them. Some will be shipped on the center beam flat cars, although some may be shipped in the 'all door' box cars. For now we'll keep it simple and have them shipped on the center beam flats.

# Setting the Default Yard

Before we start to enter any cars, we need to do a bit more housekeeping. ProTrak has a "Default yard location" data field which is where any new car put on the railroad is first placed. Before we enter any cars we need to set that up.

1. From the ProTrak toolbar, click on "Administration" then select "SPOT Format and special SPOTs" from the dropdown list. The window shown in Figure 7-1 will be displayed.

Interchange track code	\$	Special spot codes
Primary receiving track	98 👤	"x", cleaning track used 🛛 🕥 Yes 🔿 No
Primary delivery track	99 💌	
Second receiving track	97 💌	"r", car RIP track used 🛛 🔍 Yes 🔿 No
Second delivery track	96 💌	"r", car repair shop used 🔰 🤆 Yes 🔹 No
Default yard location —		"z", weigh scales in use 💽 🔍 Yes 🔿 No
A freight car's first location		
A passenger car's first locati	on ACT-01 🗾	"s" is staging track "t" is a team track, or general use track
		"v" is a vard track, or set out track
Default staging for priva	ste cars	"L" is a lead track
Derault nome point for privat	e car not valid	
Car ferry on main track		
A car ferry is use to move ca	ars between stations on r	nain track. 🕜 Yes 💿 No
Narrow Gage Subdivisio		
Hailroad has a harrow gage	subdivision. Lading is tr	ansfered between cars. C Yes (• No

Figure 7-1

2. At the bottom of the window, near the right-hand side are two buttons – Unlock and Apply. As you can see, the "Apply" button is 'grayed out' making it inoperable. In order to make changes you must first click on the "Unlock" button. Since making changes here is global, and can have some serious consequences, you will now get the warning message shown in Figure 7-2.

Settings	in use!				×
8	If you make any change in these spot forma	at settings you w	vill need to manu	ally change all waybills and customers.	. Unlock settings?
		Yes	No	]	

Figure 7-2

Click on "Yes" and you will now see that the "Unlock" button has disappeared, and the "Apply" button is no longer 'grayed out'.

3. If you look at the "A freight car's first location" data field, you may see "ACT-Yd". If "ACT-Yd" is not displayed, click on the dropdown arrow beside the data field and select "ACT-Yd" from the list. Figure 7-3 shows the window after this change.

Interchange track code	\$	Special spot co	des		
Primary receiving track	98 💌	"x", cleaning track	used	· Yes	C No
Primary delivery track	99 💌				
Second receiving track	97 💌	"r", car RIP track	used	• Yes	C No
Second delivery track	96 💌	"r", car repair sho	o used	C Yes	
Default yard location —		"z" weigh scales	in use	• Yes	C No
A freight car's first location	► BY-TDA				
A passenger car's first locati	on ACT-01 👻	"s" is staging tra	nck		
	-	"t" is a team tra	ck, or g	eneral (	use track
Default staging for priva	ate cars	"y" is a yard tra	ck, or se	et out ti	ack
Default home point for privat	e car not valid 🛛 💌	"L" is a lead tra	ck		
Car ferry on main track					
A car ferry is use to move ca	ars between stations on m	ain track.	C Yes		<u>.</u>
Narrow Gage Subdivisio	n				
Bailroad has a narrow gage	subdivision. Lading is tra	nsfered between cars.	C Yes	G No	<b>.</b>

Figure 7-3

- 4. Similarly, the data field "A passenger car's first location" should be set to "ACT-01 if it is not already set to that. Remember that the passenger station is always track 01. (For now, we can ignore the remainder of the items in this window.)
- Once both of the fields in the "Default yard location" area read as discussed in paras 3 and 4, click on "Apply" to finalize the changes. The "SPOT or ZTS (Zone/Track/Spot) Code Formats" window will close and we can continue.

# Adding Cars

Now that we've got that housekeeping item out of the way, let's enter some cars. For Wilson and Sons, we'll start off with two gondolas, so let's enter that data.

1. From the ProTrak toolbar, click on "Traffic" then select "Freight and passenger cars" from the dropdown list. The window shown in Figure 7-4 will be displayed.

🕙 Rollii	ng stock (Cars)														X
#	Initials	Number	Kind	NG	Lgh	LdLmt	Contents	BoL	Hrs	Spot	Next	Dest'n	Quality	Traffic	

Figure 7-4

1. This window will likely have the window shown in Figure 7-5 displayed on top of it (the car number and reporting marks may be different).



Figure 7-5

2. Click on "Yes" to correct the SPOTs. This message has been caused by us eliminating various customers (and of course the corresponding SPOTs) as we set up the customers for our railroad in Chapter 6.

3. Figure 7-6 shows the first part of what the window would look like with all of the data from the sample railroad loaded <sup>(1)</sup> (A larger version of Figure 7-6 can be found in Appendix C).

#	Initials	Number	Kind	NG	Lgh	LdLmt	Contents	BoL	Hrs	Spot	Next	Dest'n		Traffic
Ê.	THB	3667	XM		44	82	mty	0		ACT-Yd	ACT-Yd	ACT-Yd	Α	Chicago, IL at: CHI02s
2	EBAX	6008	T103AN		45	60	mty	0		NYCH	NYC01s	NYC01s		New York, NY at: N
3	CR	564431	GB		57	66	de-activated	0	S: 14					
1	C&O	19209	XL		45	63	mty	0		ACT-Yd	ACT-Yd	ACT-Yd	Α	
5	CP	85697	XM		55	78	mty	0		NYCH	NYC01s	NYC01s	A	New York, NY at: N
6	BN	275012	XF		68	86	mty	0		ACT-Yd	ACT-Yd	ACT-Yd	A	apples
7	ABT	412	RS		38	39	mty	0		ACT-Yd	ACT-Yd	ACT-Yd	A	St Louis, MD at: ST
3	GTW	516023	XM		45	69	mty	0		ACT-Yd	ACT-Yd	ACT-Yd	Y	
9	PBB	24285	XM		44	62	de-activated	0	S: 12				X	
0	BCOL	10	FBC		57	66	mty	0		ACT-Yd	ACT-Yd	ACT-Yd		
1	DL&W	55699	XM		44	66	mty	0		ACT-Yd	ACT-Yd	ACT-Yd	Y	
2	NSOL	5437	XM		56	81	mtu	0		ACT-Yd	ACT-Yd	ACT-Yd	X	
3	NSOL	4069	XM		45	66	mtu	n.		bY-TOA	bY-TOA	bY-TOA	A	
4	B&O	9003	EDW/		52	1302	de-activated	Ő	S:13	1.01.10	110110	iner re		New York, NY at: N
5	BLO	350458	GB		57	96	mhu	Ő	0.10	ACT-Yd	ACT-Yd	ACT-Yd		How Fore, I'l de H
6	BM	700049	XM		54	79	mty	ñ		ACT-Yd	ACT-Yd	ACT-Yd	X	
7	NSOLL	60056	10		38	80	mtu	ñ		ACT.Yd	ACT-Yd	ACT-Yd		
8	NSOL	9234	GB		45	68	scrap iron	62		NYCH	CHI02s	CHI02e		××∩V
a	CLC	4096	VI.		56	79	scrap non	0		ACT.Yd	ACT.Yd	ACT.Yd	V	07
20	NSOLL	9224	GB		45	69	rotu	0		ACT.Yd	ACT-Yd	ACT.Yd	0	
21	DEE	46000	DC		4.5	50	my	0		ACT.Vd	ACTIVA	ACTIVA		Chiesee II at CHI02
22	CLIDV	40000	10		F0	00	my	0		ACTIVA	ACTIVA	ACTIVA	~	Chicago, it al. Chioza
22		40073	EC		53	107	nty	0		×Ourser	000 VJ	000 VA		SCEDUIS, MO al. ST
2.0	LID	E271E	FC		00	70	my	0		ACTIVA	ACT V-	ACT VA		
14	UF MEC	05710	PL VI		03	01	my	0		ACTIVA	ACTIV	ACTIVA		
20	COLL	20120	AM LO		44	70	my	0		ACTVA	ACTIVA	ACTIVA	A	
17	11110	34724	LU T10764		32	70	my	0		AUT-TO MMCU	AUT-TO	AUT-TO		
10	DTDV	79483	T103W		41	21	my	0		NYCH	NYCOIS	NYCO1		
28	DIUX	38134	TTU3A		41	21	mty	0	0.40	NYCH	NYCOIS	NYLUIS		
3	D&H	15237	GB		57	99	de-activated	U	5:12	LOTILL	LOTILL	LOTILL		
5U	NSUU	5437	XM		55	81	mty	U		ALT-Yd	ACT-Yd	ALT-Yd	A	OL: U OLUGO
51	NSUU	1989	LU		51	79	mty	U		ALT-Yd	ALT-Yd	ALT-Yd		Chicago, IL at: CHIU2:
32	NSUU	60/1	XM		44	68	mty	U		ACT-Yd	AUT-Yd	ACT-Yd	X	
33	NSUU	50671	GB		45	68	mty	U		ACT-Yd	AUT-Yd	AUT-Yd		
34	NSOU	6626	SM		45	64	mty	0		ACT-Yd	ACT-Yd	ACT-Yd		
35	NSOU	6506	SM		44	47	mty	0		ACT-Yd	ACT-Yd	ACT-Yd		
36	NP	1056	XM		45	67	de-activated	29	S: 13				2442	**OV
37	CLP	3042	XM		54	79	mty	0		ACT-Yd	ACT-Yd	ACT-Yd	A	
38	LVRC	5371	XM		52	82	de-activated	0	S: 14				A	talc, crude
39	SCL	90928	XM		54	77	mty	0		ACT-Yd	ACT-Yd	ACT-Yd	X	
10	NSOU	2378	T103A		46	53	mty	0		ACT-Yd	ACT-Yd	ACT-Yd		
11	MILW	3804	XM		54	80	mty	0		ACT-Yd	ACT-Yd	ACT-Yd	X	
12	C&O	619112	LO		53	96	de-activated	0	S: 14					

Figure 7-6

Before we continue on, let's take a moment to briefly discuss the buttons on the bottom of the window:

- Change a car once a car is selected by clicking on the appropriate number in the first column, if you click on this button, the "Changing Car" window is displayed. You can also activate the "Changing Car" window by double-clicking on the car in the "Rolling stock (Cars)" window.
- Single new car allows the entry of a single car

<sup>&</sup>lt;sup>1</sup> If you **right**-click on an empty portion of the window, a tool tip will appear.

- Multiple copies allows you to add several copies of identical (except for the car number) cars at once without having to enter a lot of data again and again. Useful if you are adding cars for a unit coal train as an example.
- De-activate Car allows the car to remain on file for the railroad, but makes it unavailable to ProTrak for use. More on this later in the manual.
- Un-restrict Car allows you to remove a restriction, such as a car in captive service or a restriction on the commodity to be carried.
- Check Cars checks each of the routing locations for each car to make sure they are one of:
  - A valid staging track
  - A valid customer siding number (SPOT)
  - A valid train symbol.

In other words make sure that anywhere where a car is located at or routed to is valid  $^{(2)}$ .

Since there are a whole lot more cars than we want to start with, let's reduce the number in this list first to just 2 (the smallest number of cars that we can have). Click on "Close" to close this window and then we'll go ahead and reduce the number of cars on file.

1. Click on "Administration" on the ProTrak toolbar and then choose "Limits on Equipment, Railroad & Traffic" from the dropdown list. You are already familiar with the window shown in Figure 7-7 as we've used it before.

<sup>&</sup>lt;sup>2</sup> On startup, ProTrak does the same check of the three items that the "Check Cars": button does, however it only reports "You have X cars with invalid data and this will cause a problem". Using the "Check Cars" function will allow you to identify which car(s) have a problem.

* To add NEW data, g lists the item and sele	o to the ect "Edi Availab	approp t", "Ne <mark>le                                     </mark>	vriate s w". In Use	ecti	ion which
Freight and passenger cars	107	Set to:	107		
Containers and vans	26	Set to:	26		
Locomotives or units	23	Set to:	19	÷	
Cabooses	7	Set to:	7	÷	
Main line stations	7	Set to:	6	÷	
Staging tracks	4	Set to:	4	÷	
Online customers	10	Set to:	10	-	
Bills-of-Lading/waybills	72	Set to:	72		
Train jobs	3	Set to:	3	•	
<u>Cancel</u>					<u>o</u> k
De-Activate all Fou	ioment				

Figure 7-7

- Click on the data field "Freight and passenger cars" (the first field in the list) and change the value to "2", either by using the up and down arrows at the side of the data field, or by erasing the current value (mine says 107) and entering "2" in its place.
- 3. Click on "OK" to apply the change. You'll then be asked to confirm and re-confirm the change (Figures 7-8 and 7-9).







Figure 7-9

Once you click on "Yes" twice, all of the existing cars except the first two will be deleted. It is important to pay attention to these confirmation messages, as a failure to do so may result in erasing valuable data, and there is no "Undo" button! Also, note that once you've clicked on "Yes" the second time, the "Setting Operating Limits" window will automatically close.

You can see that there are two ways to remove unwanted data – delete the individual entries as we did with the customers or using the "Setting Operating Limits" window, change the maximum value. Which you use will depend on the situation. In the case of the customers, we needed to delete selected customers interspersed in the list so deleting line by line is the most appropriate way. In the case of cars, we're going to enter all of the data from scratch so we'll use the adjusted limits method.

- 4. OK, let's actually get started entering data. We'll do the two gondolas for "Wilson & Sons". Again click on "Traffic" on the ProTrak toolbar, then choose "Freight and passenger cars" from the dropdown list.
- 5. You may now see the message in Figure 7-10.



Figure 7-10

6. If asked the question in step 5 above, answer "Yes". Figure 7-11 shows what the "Rolling stock (Cars) window should look like once the update has completed.

#	Initials	Number	Kind	NG	Lgh	LdLmt	Contents	BoL	Hrs	Spot	Next	Dest'n	Quality	Traffic
1	THB	3667	XM		44	82	mty	0		ACT-Yd	ACT-Yd	ACT-Yd	A	Chicago, IL at: CHI02s
2	EBAX	6008	T103AN		45	60	mty	0		NYCH	NYC01s	NYC01s		New York, NY at: NYC01:

Figure 7-11

- 7. As you can see from Figure 7-11, both of the remaining cars have staging tracks ("CHI02s" and "NYC01s") shown in the "Traffic" column. If we don't remove these entries, we will get an "invalid" spot" message every time we go in to do any work on any of the cars. Here's what we need to do to fix the problem:
  - a. Double-click on car #1. The window shown in Figure 7-12 will appear

Car Description				Railro	ads in Officia	al Guide	
Reporting marks THB	Car kind	ХМ		###	Initial	Railroad	
Number 3667	Car class	ХМ		1 2 2	PRO ATSF	ProTrak Demonstrator Atchinson, Topeka & Purilinaten Matthem	
1 an all an an an allow the later	- Plata Co			4	CR	Conrail	
Length over couplers, it 44	Fiate [L		<b>_</b>	5	CSX	Chesapeake Seaboard	
Volume, cuft 2500				6	NS	Norfolk Southern Rai	
Diale date	Constant II	0100	000	6	SP	Southern Pacific	
	Gloss wgt, it	JS <b>210</b> ,	000	°.		CD D -: I	
Bearing D 210 000 lbs -	Light Weight	lbs 56.3	00	10	CP CP	Canadian Pacific	
	Eight Holgh,	100 100,0	00	11	CN	Canadian National	
Bearing kind Friction -	Load Limit, Ib	s 163.	700	12	ASEC	Atlantic & East Caro	
	2 competition and the	No. Distant		13	Ad	Ann Arbor	
-Restrictions, if any			14	14	20	Michigan Interstate	
When empty route to" (I eas	ee or owning rails			15	AC	Algoma Central	
in on physical and the feed	oo or or nining rail			16	ACL	Atlantic Coast Line	
Return Empty Top Chicag	o, IL	CHI	02s	17	AD	Atlantic & Danville	
Car ownership (Boute to)		and in		18	ADN	Ashley Drew & North	
Car ownership (riocite to) 100	her or reporting m	Iarks		19		Almanor Bailroad	
I ading Destrictions (Lond only	r -			20	ALM	Arkansas & Louisiana	
Laung Restrictions (Load only	r			21	ALS	Alton & Southern	
Load restricted to wheat	lour	20	411	22	AMB	Aracata and Mad Bive	
Bestrictions on use P		Out	slitu A	23	ΔN	Analachicola Norther	
Hestiletons on use		Qui	and a	24	ANB	Angelina & Neches Bi	
				25	APA	Anache	
Present Assignment			-	26	AB	Aberdeen & Bockfish	
Waubill 0 Contonto	SHI.	In terms		27	ABA	Arcade and Attica	
Contents	inty	10 tons		28	ARC	Alexander	
Location of CHNY	B-end fac	es East	-	29	ABT	American Refrigerato	
	and the second sec	- Internet		30	ASAB	Atlanta & St Andrews	
Lonsignee is Chicago, IL	at	CHI02s		31	ATW	Atlantic & Western	
				32	AVL	Aroostook Valley	
Model Characteristics				33	AWW	Algers, Winslow and	
Weight of model car, oz 4.50	Rolling resi	stance, %	1.0	Show	Private L	ines	
Model last inspected on 24	Mar •	2014	-	Und	heck for Ma	nual Data Entry	

Figure 7-12

- b. Note that the "Location of car" data field (about two-thirds of the way down in the left hand panel) shows "CHNY". We need to change the location to show that it is in ACT yard so click in the "Location of car" data field then double-click on "ACT-Yd" in the right hand panel.
- c. Click on the "Return Empty To" field (about half ways down the left hand panel) and erase the data in that field.
- d. Click on OK  $^{(3)}$ .
- e. To clear up the problem with car # 2, double-click on line 2 and repeat steps 7b through 7d.

Figure 7-13 shows what the "Rolling Stock (Cars)" window will now look like once you have corrected the problems with the two cars. You will notice that the "Traffic" column now shows the load restriction for the car rather than the staging track it was to be returned to when empty.

<sup>&</sup>lt;sup>3</sup> Once you have blanked out the "Return Empty To" data field, ProTrak will update it with the phrase "Home road via connection". Any car which has the "Return Empty To" data field showing either spaces or the phrase "Home road via connection" is treated as being unrestricted.

5	Ro	olling stoc	:k (Cars)												
	#	Initials	Number	Kind	NG	Lgh	LdLmt	Contents	BoL	Hrs	Spot	Next	Dest'n	Quality	Traffic
	1	THB	3667	XM		44	82	mty	0		ACT-Yd	ACT-Yd	ACT-Yd	A	wheat flour
	2	EBAX	6008	T103AN		45	60	mty	0		ACT-Yd	ACT-Yd	ACT-Yd		anti knock comp

Figure 7-13

8. Now on to adding new cars. On the ProTrak toolbar, click on "Edit" then choose "New car" from the dropdown list. You'll now see the window shown in Figure 7-14a<sup>(4)</sup>.



Figure 7-14a

There's a lot of information here, but not all of it is required in order to make things move. We'll only enter what is necessary, and briefly discuss some of the other items. Have Table 3 from Appendix B ready and let's set about entering the data for a car. We'll do car # 3 in Table 3 (cars 1 and 2 are left over from the original ProTrak sample data). For simplicity

<sup>&</sup>lt;sup>4</sup> The field labeled "Model car is owned by" will contain the name you entered in the registration window when installing ProTrak.

sake, initially we'll refer to Figure 7-14a for pointers to the data fields to be changed. Later when we discuss other items which are not being changed, we'll refer to Figure 7-14b.

- 9. Click on the "Reporting marks" (tt) data field and from the list in the right-hand panel, double-click on "WC Wisconsin Central"
- 10. Click on the "Car kind" (tt) data field and from the list in the right-hand panel, double-click on "GB" <sup>(5) (6)</sup>. In our case the type we wanted GB was listed. If the type we wanted was not listed (GBSR for example), click on the general type for that car (in this case G), then click on the radio button marked "Show ... Specific kind" to see all of the sub types for that general type. The list in the right hand panel now shows all of the specific cars of that general kind. Double-click on the car kind you desire, in this case GB. You will notice that both the "Car kind" and "Car class" data fields were updated.
- 11. Click on the "Number" (tt) data field and replace the "3" with the number of our car "55161".
- 12. The "Length over couplers" (tt) data field is also important to us at this point. This data field is used to calculate whether there is room in a siding for another car. Click on the "Length over couplers" data field and replace the existing value with "57" <sup>(7)</sup>.
- 13. The "Volume" data field also needs to be looked at. This data field controls which cars are used to take a particular shipment. We'll get into this more when we discuss waybills in Chapter 8. Looking at Table 3 in Appendix B you will note that only enclosed or semi-enclosed (gondolas and hoppers) cars have a volume data. Flat cars of all varieties do not and ProTrak will not ask you to enter a "Volume" figure. Click on the "Volume" data field and replace the existing value with "2324"

<sup>&</sup>lt;sup>5</sup> AAR Mechanical type. For more info on AAR Mechanical types the web sites at http://www.nakina.net/aartype.html and www.greatnorthernempire.net/GNE\_AARCarCodes.htm are two of many that have a good description of the various types.

<sup>&</sup>lt;sup>6</sup> The list of car types can be updated to reflect a different era by clicking on the "Car kind" data field, then from the ProTrak toolbar choose Edit/Change/Change Car Mechanical Kind list.

<sup>&</sup>lt;sup>7</sup> The "length over couplers" is usually the nominal length of the car (i.e the "EX LEN" figure on the car) plus 4 feet for the couplers. You may wish to actually measure the length of the cars over the coupler pulling face to get an exact figure as had been done for the cars in our railroad.

- 14. Click on the "Return Empty To" data field. This data field controls how the car is routed when empty <sup>(8)</sup>. In order to make sure that there are no restrictions on the car, if anything other than "Home road via connection" or "PRO car distributor" is shown we'll just blank this data field out. Blanking out the "Return Empty to" data field will cause ProTrak to automatically insert either the phrase "Home road via connection" or the phrase "PRO car distributor" and may also cause the "Restriction on use" data field to have a "U" inserted. "U" means the car is unrestricted.
- 15. At this point, we have enough information to allow the car to be moved, we'll accept the defaults as supplied by ProTrak, for the other data fields, however let's look at some of them. Figure 7-14b has the pointers to the following data fields.
  - a. Plate (tt) defines the vertical and horizontal clearances that this car requires to pass along the track.
  - b. Built date self explanatory. ProTrak will use this when checking some of the other data entered, to make sure it makes sense from a time perspective.
  - c. Bearing (tt) the maximum weight that the bearings on this car are designed to handle. Most pre-1960 cars have "D" bearings, while most of those built after this period have "E" bearings. This field must have a value in it for ProTrak to use the car.
  - d. Light Weight, lbs (tt) in most cases this will be printed on the car and indicates the weight of the car without any load. Required field.
  - e. Bearing kind (tt) self explanatory, either friction or roller. Required field <sup>(9)</sup>.
  - f. Load restricted to (tt), and Restrictions on use (tt) controls how the car is used and are for the most part self explanatory (see also footnote for the "Return Empty To" data field above).
  - g. Quality this data field will be updated by ProTrak  $^{(10)}$ .

<sup>&</sup>lt;sup>8</sup> If the "Return Empty to" field is left blank or contains the phrase "Home road via connection", the car can be loaded at any SPOT or staging. Entering "Agent's Pool" will restrict it to loading at one station only. ProTrak automatically inserts the "Home road via connection" phrase whenever there is no specific return empty to directions.

<sup>&</sup>lt;sup>9</sup> ProTrak will reject any car with Friction Bearings if the car has a Built Date of Aug 68 or later if that car is in interchange service (i.e. not an On Company Service – OCS - car). If it is a passenger car, the date when roller bearings were required is 1950 if the car weighed over 220,000 lbs. Also, in certain circumstances, the bearing type may impact the order that cars are blocked on a train.

<sup>&</sup>lt;sup>10</sup> All cars are graded as to quality: "A", "B", "C" and "D", "K" and "U" for gondolas. Cars degrade over time so as a car is in service longer and longer; the quality will down grade from "A" to "B" then eventually "B" to "C". In addition, you may see "X", "Y" and "Z" appear in the Quality data field. "X" is an "A" car that has debris left over from the previous shipment. Similarly "Y" is a "B"

- h. Waybill (tt) this data field will be updated by ProTrak and should always be left as 0 (zero) when a new car is added to the layout. The Contents data field will also be updated by ProTrak when a wavbill is assigned.
- i. Location of Car (tt) again, self explanatory. The initial location of the car will be the default yard that we defined previously. This field will be updated by ProTrak.
- j. B-end faces (tt) the "B" end is the end that has the brake wheel on it. For the most part, this data field is cosmetic for ProTrak use. It is only used in a very advanced feature <sup>(11)</sup>.
- k. Consignee is where the car is going/is at. Updated by ProTrak.
- I. Weight of Model (tt) If the weight is set to zero, the car is deactivated. The Model weight is used to determine if the model train power units can pull the train of model cars.
- m. Rolling resistance, % (tt) Rolling resistance is used to calculate the tractive effort that the model locomotive must have to pull the train. Use a value of 1%, unless you know the car is "hard rolling" or vou have made a measurement  $^{(12)}$ .
- n. Model last inspected on When a new car is added, the date will be the current date. This date can be updated if the car is removed for inspection/repair/etc.
- o. Model car is owned by (tt) this should default to the name that you supplied when you first installed ProTrak. If the car belongs to someone else, you may want to insert that name in place of your own. If you wish to change the name, you must uncheck the box labeled "Uncheck for Manual Data Entry" at the bottom of the righthand panel. (If you don't do this, any data you enter will be ignored).

car and "Z" is a "C" car with debris left over from the previous shipment. The quality status only affect operations if a) you have a cleaning track set up, and b) the car-cleaning option is turned on under Admin/Special SPOTs. <sup>11</sup> The 'Unload from this side only' feature.

<sup>&</sup>lt;sup>12</sup> Rolling resistance is also used in working out the potential for stringlining cars within a train (see Appendix B for a definition of stringlining). In HO, typical values of rolling resistance vary from 0.5% up to 2% with 1% being an average value for models dating from the mid 80s on. A hard rolling car may have a rolling resistance of 2%. Rolling resistance can be checked by placing a car on a known grade, letting it go and seeing if it starts to move.

	Changing active can 3 of: 3	
	Car Description	
	Reporting marks WC Car kind GB	
	Number 55161 Car class GB	0 No online data 0
	Length over couplers. It 57 Plate C	15a
	Volume, cult [2324]	0
b —	Built date Nov  1973 Gross Wgt. bs 220,000	0
c —	Bearing D 220,000 lbs - Light Weight, lbs 56,300	15d
e —	Bearing kind Roller - Load Limit, bs 162:700	
5f —	Car ownership (Route to) owner of reporting marks  Lading Restrictions (Load only) Load restricted to Restrictions on use Quality	15g
	Present Assignment	15
h —	Waybil 0 Contents may Ditons	13]
i —	Location of car ACT-Yd B-end faces East	15m
k —	Consignee is first shippet	
	Model Characteristics	
51	Weight of model car, oz 4.00 Rolling resistance, % 1.0	
in—	Model last inspected on 16 + Mar + 2014 +	Uncheck for Manual Data Entry
io	Model car is owned by John Smith	
		Cancel OK De-activate Invento

Figure 7-14b

In addition, at the bottom of the right-hand panel there is a button marked "Inventory" This allows you to provide more information which is useful from an inventory standpoint (date purchased, for example) but is not used by ProTrak for railroad operations.

16. Figure 7-15 shows what your "Changing active car: 3 of: 3" window should look like once you've changed the data as shown above. Note that the name in the "Model car is owned by" and "Model last inspected on" data fields will likely be different. The "Consignee is" data field and the data in the right-hand panel may also be different.

Changing active car: 3 of: 3		le l
Car Description		
Reporting marks WC	Carkind GB	
Number 55161	Car class GB	0 No online data 0
ength over couplers, ft 57	Plate C 🗸	
uilt date Nov - 1973 -	Gross Wgt, Ibs 220,000	
earing D 220,000 lbs 💌	Light Weight, Ibs 56,300	0
Bearing kind Roller 🚽	Load Limit, Ibs 163,700	
Return Empty To     Home ro       Car ownership (Route to)     own       Lading Restrictions (Load only)     Load restricted to       Restrictions on use	oad via connections er of reporting marks e	
Present Assignment		
Waybill 0 Contents	nty O tons	
Location of car ACT-Yd	B-end faces East	
Consignee is first shipper	at ACT Ya	
Model Characteristics		
Weight of model car, oz 4.00	Rolling resistance, % 1.0	
Model last inspected on 16 🛫	Mar 🔻 2014 💌	Uncheck for Manual Data Entry
Model car is owned by John S	mith	Cancel OK De-activate Inventor



- 17. If everything is correct, click on "OK" to make these changes take effect and return to the "Rolling stock (Cars)" window.
- 18. We need to add a 2<sup>nd</sup> gondola the one identified as car 4 in the Freight Car Information table (Appendix B, Table 3). Since this car is almost identical to the car we've just entered (only the reporting marks and car number differ), we can use a feature of ProTrak to copy the car we just entered to create a clone of it. In the "Rolling stock (Cars)" window, click on line 3; the one with the Wisconsin Central gondola in it.
- 19. Click on the button marked "Multiple copies" down at the bottom of the window. The window shown in Figure 7-16 will appear

ase car		New numbers
load initials	WC	Number car 2)
Number car 1)	55161	Number car 3)
echanical kind	GB	Number car 4)
Length, feet	57	Number car 5)
Capacity, tons	81.9	Number car 6)
		Number car 7)
How many add	itional cars	Number car 8)
How many additio	nal cars 5 💌	Number car 9)
Consel	or I	Number car 10)
		Number car 11)
		Number en 12)

Figure 7-16

20. Change the value in the "How Many additional cars" data field to 1, either by entering the value directly, or by using the up and down arrows beside the data field. Click on the "OK" button immediately below the number of cars to be added data field and the window will change to look like Figure 7-17.

load initials lumber car 1) echanical kind	WC 55161	Number car 2)	
Number car 1) Mechanical kind	55161		
Mechanical kind			
	GB		
Length, feet	57		
Capacity, tons	81.9		
C Generate a ran C Generate a seq	ge of car numbers juence of numbers		

Figure 7-17

21. You will notice two things: The right-hand panel now has only one data field shown, and the box at the bottom of the left hand panel has been replaced with one labeled "How to get car numbers". In that box, click on the "You will input all car numbers" radio button. The "Multiple new cars" window changes again, to look like Figure 7-18.

	- 10 M - 10 M	New numbers	
Road initials	WC	Number car 2)	
Number car 1)	55161		
Mechanical kind	GB		
Length, feet	57		
Capacity, tons	81.9		
Generate a ra Generate a ra Generate a se Input car numb	all car numbers inge of car numbers equence of numbers er		
Enter next car nur	nber 55161	<u>.</u>	

Figure 7-18

22. In the "Enter next car number" data field, enter the car number for car 4 - 327155, and then click on "OK". The "Input car number" box will disappear and the window will look like Figure 7-19.

lase car			
Road initials	WC	Number car 2)	327155
Number car 1)	55161		
Mechanical kind	GB		
Length, feet	57		
Capacity, tons 👘	81.9		
<ul> <li>You will input</li> <li>Generate a ra</li> </ul>	all car numbers inge of car numbers		
Generate a se	equence of numbers		

Figure 7-19

23. As you can see, the area on the left where we input the new car number has disappeared. If we were to add more than one car, that area would have remained and we would be able to add car numbers for the remaining multiple copies. Since we only have one copy, we will click on "Accept". The new car will be added and you will be returned to the "Rolling stock (Cars)" window, which should look like Figure 7-20.

5	8 Ro	lling stoc	k (Cars)												
	#	Initials	Number	Kind	NG	Lgh	LdLmt	Contents	BoL	Hrs	Spot	Next	Dest'n	Quality	Traffic
	1	THB	3667	×м		44	82	mty	0		ACT-Yd	ACT-Yd	ACT-Yd	A	wheat flour
	2	EBAX	6008	T103AN		45	60	mty	0		ACT-Yd	ACT-Yd	ACT-Yd		anti knock comp
	3	WC	55161	GB		57	82	mty	0		ACT-Yd	ACT-Yd	ACT-Yd		
	4	WC	327155	GB		57	82	mty	0		ACT-Yd	ACT-Yd	ACT-Yd		



24. There's obviously something wrong here. The reporting marks for car 4 are supposed to be "GVSR" not "WC". To correct that, double-click on line 4 and the window in Figure 7-21 will appear.

Car Description		Rai	lroads in Officia	l Guide	
eporting marks WC	Car kind GB	-	# Initial	Bailtoad	
007455	C I I I I I I I I I I I I I I I I I I I		PBO	ProTrak Demonstrator	
umber 327155	Lar class [GB	2	ATSE	Atchinson Topeka &	
		3	BN	Burlington Northern	
		4	CR	Conrail	1
ength over couplers, ft 57	Plate C	- 5	CSX	Chesapeake Seaboard	
olume cuft 2324		6	NS	Norfolk Southern Rai	
12324		7	SP	Southern Pacific	
uilt date Nov 👻 1973 👻	Gross Wgt, lbs 220	.000 8	UP	Union Pacific	
		9	CP	CP Rail	
earing D 220,000 lbs 👻	Light Weight, lbs 56,0	300 10	CP	Canadian Pacific	
	1	11	CN	Canadian National	
earing kind Roller	Load Limit, Ibs 163	.700 12	A&EC	Atlantic & East Caro	
		13	AA	Ann Arbor	
festrictions, if any	5. 20 B.	14	AA	Michigan Interstate	
"When empty, route to" (Lease	e or owning railroad)	15	AC	Algoma Central	
Return Empty To Home ro	ad via connections	16	ACL	Atlantic Coast Line	
		17	AD	Atlantic & Danville	
Car ownership (Route to) owne	er of reporting marks	- 18	ADN	Ashley, Drew & North	
1		19	AL	Almanor Hailroad	
Lading Restrictions (Load only)		20	ALM	Arkansas & Louisiana	
Load restricted to		21	ALS	Alton & Southern	
			AMH	Aracata and Mad Hive	
Hestrictions on use	UL UL	iality A	AN	Apalachicola Norther	
10 A		24	ANH	Angelina & Neches Hi	
Propert Assignment		25	APA	Apache	
Tesent Assignment		25	AR	Aberdeen & Rocklish	
Vaybill 0 Contents m	ity 0 tons	27	ADA	Arcade and Attica	
ocation of car ACT VA	Biend faces East	- 20	ADT	Alexandel American Bafrigerate	
ACT-TO	D characes [Last	23	ACAD	Attendari Neingeratu	
onsignee is	at ACT-Yo	21	ACAD	Atlantia & Western	
		- 37	AVI	Atlantic & Western	
odel Characteristics		32	AUAU	Algers Winslow and	
	1 2 2 2 AM		A****	Algers, winslow and	
/eight of model car, oz 4.00	Rolling resistance, %	1.0 Sho	w 💽 Private Li	nes	
and the state of the local state of the stat			Inchask for Mar	anal Data Eatra	
oder last inspected on 16	Mar 2014		meneck for Mar	nuar Data Entry	
to the second					

Figure 7-21

- 25. Click on the "Reporting marks" (tt) data field, then from the right-hand panel scroll down and look for "GVSR". As you can see, there is no entry for "GVSR" so we'll enter it manually <sup>(13)</sup>.
- 26. Click on the "Reporting marks" data field, erase the existing "WC" and type in "GVSR".
- 27. The "Volume" data field is also incorrect. Click on the "Volume" data field and change the value to read "2244". Your window should now look like Figure 7-22

<sup>&</sup>lt;sup>13</sup> This is one case where we need not worry about the "Uncheck for Manual Data Entry" setting.

ar Descripti	on								
eporting marks	GVSR	Car kind	GB		###				
lumber	327155	Car class	GB		0	No online data			
					Ő				
ength over cou	iplers, ft 57	Plate C		-	0				
/olume, cuft	2244				0				
Built date	ov 💌 1973 💌	Gross Wgt,	lbs 220,	000	Ő				
Bearing D	220,000 lbs 👻	Light Weigh	nt, Ibs 56,3	300	0				
Bearing kind	Roller 💌	Load Limit,	lbs <b>163</b> ,	700					
-Lading Restric Load restricte Restrictions o	tions (Load only) d to		] Qu	ality A					
Present Assig	inment		in con						
ocation of car	ACT-Yd	B-end fa	ces Fast						
Consignee is			at ACT-Yd						
Model Chara	teristics						m	 2	
Weight of mode	car, oz 4.00	Rolling re	sistance, %	1.0	P				
dodel last inspe	cted on 16 🗨	Mar	▼ 2014	-	Unc	heck for Manua	Data Entry		
					test.				

Figure 7-22

28. Click on "OK" to accept the change and return to the "Rolling stock (Cars)" window. It should now look like Figure 7-23.

Ē	🛛 Ro	lling stoc	k (Cars)												
	#	Initials	Number	Kind	NG	Lgh	LdLmt	Contents	BoL	Hrs	Spot	Next	Dest'n	Quality	Traffic
	1	THB	3667	×м		44	82	mty	0		ACT-Yd	ACT-Yd	ACT-Yd	A	wheat flour
	2	EBAX	6008	T103AN		45	60	mty	0		ACT-Yd	ACT-Yd	ACT-Yd		anti knock comp
	3	WC	55161	GB		57	82	mty	0		ACT-Yd	ACT-Yd	ACT-Yd		
	4	GVSR	327155	GB		57	82	mty	0		ACT-Yd	ACT-Yd	ACT-Yd		



We used the duplication technique here to show you how it works. Obviously, it would have likely been just as fast to have just gone through the normal "Single new car" process, as we did with the first car we entered. This duplication technique is normally used to input a bunch of cars which are identical except for the car number. There is a 2nd way to duplicate a car and we'll use that later on.

- 29. Let's go ahead and enter another car car number 5 using the data from Appendix B Table 3. Follow the process in steps 8 through 14 above (you'll have to enter the reporting marks manually), substituting the data from the table for car 5. Once all of the data is entered, click on "OK" to accept the data and return to the "Rolling Stock (Cars)" window.
- 30. Now that car 5 has been entered, we could follow the same procedure for car 6. From looking at the list, it is obvious that car 6, with the exception of reporting marks, car number and volume, is identical to car 5. We could duplicate it using the "Multiple copies" process that we've used for the GVSR gondola, but there is another way, this time much easier. Click on line 5 which is the MRL box car you just entered. From the ProTrak toolbar, click on "Edit" then select "Copy a car" from the dropdown list. You should see a window which looks like Figure 7-24.

Schanging active car: 6 of	: 6					×
Reporting marks MRL	Car kind	XM	Railroa	ds in Offi	cial Guide	
Number 3004	Car class	XM	###	Initial	Railroad	^
			2	ATSF	ProTrak Demonstrator Atchinson, Topeka &	
	DL. D		3	BN	Burlington Northern	
Length over couplers, rt 55	Plate JL	<u> </u>	5	CSX	Chesapeake Seaboard	
Volume, cutt [6156			6	NS SP	Norfolk Southern Rai Southern Pacific	
Built date Nov 💌 1973 💌	Gross Wgt, Ibs	220,000	8	UP	Union Pacific	
Bearing D 220 000 lbs V	Light Weight	lbs 56 300	9	CP	CP Rail Considian Pacific	
			11	CN	Canadian National	
Bearing kind Roller	Load Limit, Ibs	163,700	12	A&EC	Atlantic & East Caro	
Return Empty To Home road	via connections		14	AA	Michigan Interstate	
Load restricted to			15	AC	Algoma Central	
Restrictions on use	1	Quality A	17	AD	Atlantic & Danville	
			18	ADN	Ashley, Drew & North	
Waybill 0 Contents e	mpty 	0 tons	20	ALM	Almanor Hallroad Arkansas & Louisiana	
Location of car ACT-Yd	B-end face	west 💌	21	ALS	Alton & Southern	
Consignee is first shipper	at	ACT-Yd	22	AMB	Aracata and Mad Rive	
Weight of model car, oz 4.0	Rolling resis	tance, % 1.0	Show	Private	e Lines	
Model last inspected on 7	Jan 💌	2010 💌		neck for l	Manual Data Entry	
Model car is owned by John S	mith		<u>C</u> ancel	De-a	ctivate <u>Inventory</u>	<u>o</u> k

Figure 7-24

31. Click on "Reporting marks" (tt) and change this to "UP" (it's in the list), change the car number to "170509" and finally change the volume to "4890". Click on "OK" to accept the changes.

32. Add cars 7 and 8, the two center beam flat cars <sup>(14)</sup> from Appendix B, Table 3 and when you are finished the "Rolling stock (Cars)" window should look like Figure 7-25 <sup>(15)</sup>. Remember that when you go to change the "Car kind" data field, you need to click on "FB" in the right hand panel, click in the "Show specific kind" radio button at the bottom of the right hand panel then finally double-click on "FBC" in the list in the right hand panel.

😕 R	olling sto	ck (Cars)												
#	Initials	Number	Kind	NG	Lgh	LdLmt	Contents	BoL	Hrs	Spot	Next	Dest'n	Quality	Traffic
1	THB	3667	×м		44	82	mty	0		ACT-Yd	ACT-Yd	ACT-Yd	A	wheat flour
2	EBAX	6008	T103AN		45	60	mty	0		ACT-Yd	ACT-Yd	ACT-Yd		anti knock comp
3	WC	55161	GB		57	82	mty	0		ACT-Yd	ACT-Yd	ACT-Yd		
4	GVSR	327155	GB		57	82	mty	0		ACT-Yd	ACT-Yd	ACT-Yd		
5	MRL	30004	×м		55	82	mty	0		ACT-Yd	ACT-Yd	ACT-Yd	A	
6	UP	170509	×м		55	82	mty	0		ACT-Yd	ACT-Yd	ACT-Yd	A	
7	BCIT	873075	FBC		80	82	mty	0		ACT-Yd	ACT-Yd	ACT-Yd		
8	SSAM	38710	FBC		80	82	mty	0		ACT-Yd	ACT-Yd	ACT-Yd		

Figure 7-25

33. There's one last thing to look at, and that is deleting a car. Let's add one more car. By default ProTrak will use reporting marks "PRO", car class and kind of "XM" and the car number will be the line number – in this case 9. So let's just click on "Edit" from the ProTrak toolbar, then select "New car" from the dropdown list. Once the window in Figure 7-26 appears, click on "OK to add the car.

<sup>&</sup>lt;sup>14</sup> Remember that you need to use the "Show ... Specific kind" radio button to get the FBC entry.

<sup>&</sup>lt;sup>15</sup> By default, the list of cars is displayed in the order they were entered. To see a sorted list and to access the car data sorted, on the ProTrak toolbar click on Edit/Show/Show cars sorted by road name and number (or choose one of the options from the "Show cars by specific fleets" option). You can also sort cars by clicking on a specific column header in the list of cars.

Schanging active car: 9 of	f: 9						×
Reporting marks PRO	Car kind	XM		Railroad	ls in Offici	ial Guide	
Number 9	Car class	XM		###	Initial	Railroad	~
,		J		1	PRO	ProTrak Demonstrator	
				2	ATSF	Atchinson, Topeka &	
Length ever equiplers () [50	Dista C		_	4	CB	Eunington Northeim Contail	
Length over couplets, it 50			<u> </u>	5	CSX	Chesapeake Seaboard	
Volume, cuft 5000				6	NS	Norfolk Southern Rai	
			_	7	SP	Southern Pacific	
Built date Nov - 1973 -	Gross Wgt, Ib:	s <u>220,000</u>		8	UP	Union Pacific	
Bearing D 220,000 lbs	Light Weight	be 56,200	- 11	9	CP	CP Rail Constalion De silion	
	Light Weight,	108 00,000	- 11	11		Canadian Pacific Canadian National	
Bearing kind Roller 👻	Load Limit, Ibs	163,700		12	A%EC	Atlantic & East Caro	
·			-	13	AA	Ann Arbor	
Return Empty To Home road	l via connections			14	AA	Michigan Interstate	
Load restricted to		-		15	AC	Algoma Central	
Load restricted to				16	ACL	Atlantic Coast Line	
Restrictions on use		Quality 🗛		17	AD	Atlantic & Danville	
			- 11	18	ADN	Ashley, Drew & North	
Waybill 0 Contents	mpty	0 tons		19	ALM	Almanor Hailroad	
Location of car ACT-Yd	B-end face	es West	л 🕕	20	ALM	Alkansas « Louisiana Alton & Southern	
			- 11	22	AMB	Aracata and Mad Bive	~
Lonsignee is hirst shipper	at	ACT-Yd		<			
Weight of model car, oz 4.0	Rolling resis	tance, % 1.0		Show (	) Private	Lines	
Model last inspected on 18	Jan 💌	2008 💌		Unch	eck for M	anual Data Entry	
Model car is owned by	imith						
our of the state o				<u>C</u> ancel	De-ac	tivate <u>I</u> nventory	<u>0</u> K

Figure 7-26

You'll get the warning message shown in Figure 7-27. Click on "Yes" to accept the car number



Figure 7-27

The "Rolling stock (Cars)" window should look like Figure 7-28.

🙆 F	olling sto	ck (Cars)												
#	Initials	Number	Kind	NG	Lgh	LdLmt	Contents	BoL	Hrs	Spot	Next	Dest'n	Quality	Traffic
1	THB	3667	XM		44	82	mty	0		ACT-Yd	ACT-Yd	ACT-Yd	A	wheat flour
2	EBAX	6008	T103AN		45	60	mty	0		ACT-Yd	ACT-Yd	ACT-Yd		anti knock comp
3	WC	55161	GB		57	82	mty	0		ACT-Yd	ACT-Yd	ACT-Yd		
4	GVSR	327155	GB		57	82	mty	0		ACT-Yd	ACT-Yd	ACT-Yd		
5	MRL	30004	×м		55	82	mty	0		ACT-Yd	ACT-Yd	ACT-Yd	A	
6	UP	170509	×м		55	82	mty	0		ACT-Yd	ACT-Yd	ACT-Yd	A	
7	BCIT	873075	FBC		80	82	mty	0		ACT-Yd	ACT-Yd	ACT-Yd		
8	SSAM	38710	FBC		80	82	mty	0		ACT-Yd	ACT-Yd	ACT-Yd		
9	PRO	9	×м		50	82	mty	0		ACT-Yd	ACT-Yd	ACT-Yd	A	

Figure 7-28

34. To delete the car we just entered (PRO 9), click on line 9 then on the ProTrak toolbar, click on "Edit" and from the dropdown list select "Delete a car". The window shown in Figure 7-29 will appear.

Deleting a Car		Þ
Car		
Car list number	9	
Car roadname and number	PRO 9	
Delete data at this car	listing 'slot'	
<ol> <li>blanking/deleting al</li> <li>removing former car</li> <li>deactivating the car</li> <li>deactivating the car</li> <li>Note: The 'car' slot representation of the car will be put in this s</li> </ol>	II car data, from spurs and r (slot) that car mains, and the r lot.	/or trains, was in. next new
💿 Delete car data only (Re	commended)	
Delete and Move all ca	rs in list	
Car is deleted by: 1) Car listing is deleted 2) All other cars are mo 3) Number of cars is re	wed up list one duced by one	'slot'
🔿 Delete car 'slot'		
Cancel		Delete Car

Figure 7-29

As you can see you have two options. The actions that happen are shown in green on the screen. With the "Delete car data only" radio button selected, press on the "Delete Car" button at the bottom of the window. You're asked to confirm the delete action (Figure 7-30). Press "Yes" to make it happen.



Figure 7-30

Figure 7-31 shows what the "Rolling stock (Cars)" window will look like after the delete takes place. You'll note that there is still an entry in line 9, but there are no reporting marks and the "Contents" field reads "\*\*\* not in service".

🕙 Ro	ling stocl	c (Cars)												
#	Initials	Number	Kind	NG	Lgh	LdLmt	Contents	BoL	Hrs	Spot	Next	Dest'n	Quality	Traffic
1	THB	3667	×м		44	82	mty	0		ACT-Yd	ACT-Yd	ACT-Yd	A	wheat flour
2	EBAX	6008	T103AN		45	60	mty	0		ACT-Yd	ACT-Yd	ACT-Yd		anti knock comp
3	WC	55161	GB		57	82	mty	0		ACT-Yd	ACT-Yd	ACT-Yd		
4	GVSR	327155	GB		57	82	mty	0		ACT-Yd	ACT-Yd	ACT-Yd		
5	MRL	30004	×м		55	82	mty	0		ACT-Yd	ACT-Yd	ACT-Yd	A	
6	UP	170509	×м		55	82	mty	0		ACT-Yd	ACT-Yd	ACT-Yd	A	
7	BCIT	873075	FBC		80	82	mty	0		ACT-Yd	ACT-Yd	ACT-Yd		
8	SSAM	38710	FBC		80	82	mty	0		ACT-Yd	ACT-Yd	ACT-Yd		
9		9	×м		50	82	*** not in service	0		ACT-Yd	ACT-Yd	ACT-Yd	A	



35. Repeat step 33, but this time clicking on the "Delete car 'slot" radio button before pressing on "Delete car". Figure 7-32 shows what the "Rolling Stock (Cars)" window will look like after clicking on the "Delete car 'slot" radio button in the "Deleting a Car" window and clicking on "Yes" in the "Permanent deletion" window.

🕙 Ro	Rolling stock (Cars)													
#	Initials	Number	Kind	NG	Lgh	LdLmt	Contents	BoL	Hrs	Spot	Next	Dest'n	Quality	Traffic
1	THB	3667	×м		44	82	mty	0		ACT-Yd	ACT-Yd	ACT-Yd	A	wheat flour
2	EBAX	6008	T103AN		45	60	mty	0		ACT-Yd	ACT-Yd	ACT-Yd		anti knock comp
3	WC	55161	GB		57	82	mty	0		ACT-Yd	ACT-Yd	ACT-Yd		
4	GVSR	327155	GB		57	82	mty	0		ACT-Yd	ACT-Yd	ACT-Yd		
5	MRL	30004	×м		55	82	mty	0		ACT-Yd	ACT-Yd	ACT-Yd	A	
6	UP	170509	×м		55	82	mty	0		ACT-Yd	ACT-Yd	ACT-Yd	A	
7	BCIT	873075	FBC		80	82	mty	0		ACT-Yd	ACT-Yd	ACT-Yd		
8	SSAM	38710	FBC		80	82	mty	0		ACT-Yd	ACT-Yd	ACT-Yd		

As you can see, if you just delete the car data, the remnants of the car are left. This can be useful if you have a larger number of cars and want to keep the order of the cars in the list consistent. It is also the recommended method of deleting a car. If you delete the car 'slot' all data in that slot is removed and any cars following the one deleted are moved up in the list, thus if you delete car 9, car 10 moves to car 9, car 11 moves to car 10, etc. ProTrak uses the 'car list number' in 'marrying' various pieces of data as it prepares cars for movement. Deleting the slot has the potential to get car-at locations out of sync. As an aside, if you add a car and there is an 'empty' slot, ProTrak uses that slot for the new car.

- 36.Before we leave this section, let's do one more thing. We'll add car 9 from Table 3 (the TCAX 20115 type LU car). Once it's been entered and we're returned to the "Rolling stock (Cars)" window, we want to de-activate this car.
- 37. In the "Rolling stock (Cars)" window single click on line 9 to select the car we just entered, then at the bottom of the window, click on the "Deactivate car" button. You see that the "Contents" field contains the word "de-activated" while all of the fields that follow (BoL, etc.) are blank. This makes sense since a car which has been deactivated may have actually been removed from the layout for any one of a number of reasons. Once the car is ready to be placed back into service, it can be re-activated and we'll show you how in Chapter 12<sup>(16)</sup>.

#	Initials	Number	Kind	NG	Lgh	LdLmt	Contents	BoL	Hrs	Spot	Next	Dest'n	Quality	Traffic
1	THB	3667	XM		44	82	mty	0		ACT-Yd	ACT-Yd	ACT-Yd	A	wheat flour
2	EBAX	6008	T103AN		45	60	mty	0		ACT-Yd	ACT-Yd	ACT-Yd		anti knock comp
3	WC	55161	GB		57	82	mty	0		ACT-Yd	ACT-Yd	ACT-Yd		
4	GVSR	327155	GB		57	82	mty	0		ACT-Yd	ACT-Yd	ACT-Yd		
5	MRL	30004	XM		55	82	mty	0		ACT-Yd	ACT-Yd	ACT-Yd	A	
6	UP	170509	XM		55	82	mty	0		ACT-Yd	ACT-Yd	ACT-Yd	A	
7	BCIT	873075	FBC		80	82	mty	0		ACT-Yd	ACT-Yd	ACT-Yd		
8	SSAM	38710	FBC		80	82	mty	0		ACT-Yd	ACT-Yd	ACT-Yd		
9	TTAX	20115	LU		55	82	de-activated							

Figure 7-33

You noted that there were a number of other cars listed in Appendix B Table 3. For now we'll ignore them – they'll be used as we get further along.

One final note: We've entered car data manually for each car or duplicated it from an existing car. If you have car data in some other electronic format, there

<sup>&</sup>lt;sup>16</sup> Note that we could have de-activated the car while we were entering the data for the car. If you look at Figure 7-26 you will see a button at the bottom of the right hand panel marked "De-activate". This would accomplish the same actions as described above.

is a way to import that data. The details of how this can be accomplished is detailed in Appendix N.

38. Click on "Close" to close the "Rolling stock (Cars)" window.

### **Reporting Marks Entered Manually**

In the last section we entered a number of cars which had reporting marks that did not appear in the 'Official Guide' and therefore you had to enter them manually. While it may not be evident to you, every time you added a car which required the manual entry of the reporting marks, an entry was made in the 'Official Guide'. Since the only information available was the reporting marks, those entries are incomplete. While not necessary for the operation of ProTrak, you probably should go back in and add some of the missing data for those entries. Let's update the entries that we just made.

1. Depending on what you have done, you may find a window like the one in Figure 7-34 may be visible when you closed the "Rolling Stock (Cars)" window. If so, continue to step 3.

Railroad unknown	Hailro	ads in U	micial Guide	
Poporting marks CV/CD	###	Initial	Railroad	
reporting marks JGV5H	1	PRO	ProTrak Demonstrator	
2. ALL	2	ATSF	Atchinson, Topeka &	
rimary connection ALL	3	BN	Burlington Northern	
made at Chicago, IL	4	CR	Conrail	
	5	CSX	Chesapeake Seaboard	
Second connection	6	NS	Norfolk Southern Rai	
made at	1	SP	Southern Pacific	
	8	UP	Union Pacific	
Third connection	9	CP	CP Rail	
made at	10	CN	Lanadian Pacific	
indue at	11		Lanadian National	
Fourth connection	12	AGEL	Atlantic & East Laro	
	13		Ann Arbor Mishissa Istaatata	
made at	14	AA	Michigan Interstate	
	10	ACL	Algonia Central	
Railway Line Clearances Northeast / 1988	10	AD	Atlantic Coast Line	-
		UT.		
Lar built to AAH Plate H+ I are un-restricted.				
Maximum gross weight on rail lbs 262,000 lb				
	🔽 Un	check fo	r Manual Data Entry	

#### Figure 7-34

2. If the window shown in Figure 7-34 wasn't open, click on "The Railroad" then select "Gateways and other railroads" from the dropdown list. You will see a list of all the railroads that are in the Official Guide for the era and geographical area where your railroad is modeled. In our case, this is for 1988 in the Northeast. The railroads that have been added will be found at the extreme end of the listing so scroll down until you reach the bottom of the list. Figure 7-35 shows what this list looks like.

#	Rep Mrks	Railroad	Plate	Max Wgt	via RR	at City	via 2nd RR	at 2nd City
291	VS	Valley and Siletz	C	263,000	SP	Independence, OR	1 H	
292	VSO	Valdosta Southern	С	263,000	SR	Valdosta, GA	SCL	Valdosta, GA
293	VTB	Vermont	С	263,000	CV	Burlington, VT	GMRC	Rutland, VT
294	W&OD	Washington & Old Dominion						
295	WAB	Wabash			*N&W		NYC	
296	WAG	Wellsville, Addison & Galeton						
297	WC	Wisconsin Central	U	263,000	BN	St Paul	CP	Sault St Marie, ON
298	WLE	Wheeling & Lake Erie						
299	WM	Western Maryland	E	4 ,000	C&O	Hagerstown, MD	PLE	Pittsburgh, PA
800	WNF	Winfield	С	220,000	CR	Winfield Jct, PA		
801	WNFB	Winifrede	С	263,000	C&O	Winifrede Jct, WV		
302	WP	Western Pacific			UP	Salt Lake City	BN	Salt Lake City
103	WBWK	Warwick	С	263,000	CR	Auburn, RI		
04	WSOR	Wisconsin & Southern		1				
805	WSS	Winston-Salem Southbound	С	263,000	SR	Winston-Salem, NC	SCL	Wadesboro, NC
806	WW	Walla Walla Valley	С	263,000	BN	Walla Walla, WA		
07	YAN	Yancy	С	263,000	CRR	Kona Jct, NC	(	
808	YS	Yongstown & Southern	С	263,000	CR	Youngstown, OH	C&O	Youngstown, OH
809	YVT	Yakima Valley	С	263.000	UP	Yakima, WA	BN	Yakima, WA
10	YW	Yreka Western	F	263,000	SP	Montague		
11	GVSR	unknown	U	263,000	ALL	Chicago, IL		
312	MBL	unknown	U	263.000	ALL	Chicago, IL		
313	SSAM	unknown	U	263.000	ALL	Chicago, IL		

#### Figure 7-35

- In our case, there have been three railroads added. GVSR, MRL and SSAM. If GVSR shows "unknown" in the third column – the one titled "Railroad" – you need to update that record. If GVSR shows "Galveston Railroad, LP" then you can ignore that entry and update the next record – MRL.
- 4. To update a record, single click on the entry in the "Official Guide..." window then click on the "Change railroad" button at the lower left corner of the window. This will open the window shown in Figure 7-34.
- 5. The railroad names for the three entries are:
  - GVSR Galveston Railroad, LP
  - MRL Montana Rail Link
  - SSAM Sault Ste. Marie Bridge Company

Enter the appropriate name in the "Railroad" field then click on "OK" – we'll accept the default values for the other data. As soon you click on "OK" the "Changing Railroad" window will close.

- 6. Repeat steps 4 and 5 as often as necessary to update all three records.
- 7. Click on "Close" to close the "Official Guide..." window.

### Minimum Data Items - Cars

<u>Initials (</u>Reporting Marks) Number (Number) Class of bearing (Bearing) Weight of empty car (Light Weight) Bearing kind (Bearing kind) Model Weight (Weight of Model Car)

(See Default and Minimum Data Items in Chapter 2 for an explanation)

### **FAQs Cars**

Sections G, H, I, J and S of Appendix L have questions and answers dealing with cars and car loads. Section G also covers the issues of Gateways.

So far we've defined trains, customers and cars that are used to carry commodities to and from the customers on our railroad, but there is one last thing that needs to be done – creating waybills and associated car-orders and that is the topic we'll cover in the next chapter.

### Summary

In Chapter 7 you have done the following:

- Entered some freight cars;
- Deleted a freight car;
- De-activated a freight car;
- Set the limit the number of cars using the Administration menu;
- Added railroads to the "Official Guide".

You should also have done the following:

- Learned the importance of not entering ALL your freight cars at once;
- Learned to set the default yard;
- Learned to edit freight cars;
- Learned two ways to duplicate cars;
- Learned to delete cars from the listing:
  - Delete "Data only";
  - Delete "Complete listing";

and understood the difference between the two methods;

- Learned the two ways to de-activate a freight car;
- Learned how to update railroad records in the "Official Guide".

We've now set up some of the cars for the new railroad and can move on to Chapter 8 where we'll enter the data for waybills and car-orders needed to service the customers we set up in Chapter 6.